Resolution

Version 1.0

Version History

Version	Date	Handled by	Comments
V1.0	16-Aug-2019	ZL Chen	First version release.

Precondition Setting:

N/A

Please follow the implement as below:

Step 1:

Copy the resolution folder to your windows desktop.

Step 2:

You can found the format_reboot.bat or format.bat under the resolution folder.

If you need reboot, please run the "format_reboot.bat". Otherwise, please run the "format.bat"

Step 3:

If you run the "format_reboot.bat", please copy the counter.txt and resolution_reboot.txt to the startup folder.

If you run the "format.bat", please copy the counter.txt and resolution.txt to the startup folder.

Step 4:

Modify the wait time you want as below:

```
for /f %%i in (counter.txt) do (
    echo Counts: %%i, Date: %date%, Time: %time%
    echo Counts: %%i, Date: %date%, Time: %time% >> resolution_reboot.txt
    set counter=%%i
)

set /a counter+=1
echo %counter% > counter.txt

for /f "delims=" %%# in (
    ""wmic path Win32_VideoController get CurrentHorizontalResolution,CurrentVerticalResolution /format:value"') do (
    set "%%#">nul
)
echo The resolution is %CurrentHorizontalResolution% * %CurrentVerticalResolution%
echo The resolution is %CurrentHorizontalResolution% * %CurrentVerticalResolution% >> resolution_reboot.txt
echo The system will be reboot...
timeout /t 5
shutdown /r /t 0
```

The log as the resolution.txt or resolution_reboot.txt